

Release Note for Vigor300B

Firmware Version:	1.5.1.7
Release Type:	Important – Review release notes and upgrade if the changes affect your system stability, performance, or security
Applied Models:	Vigor300B

New Features

- None.

Improvement

- Improved: Improve Web CGI Security.

Known Issue

- The new firmware version 1.5.1.4 removes the support of the character "%" as the admin password to enhance the WebGUI security. If the character "%" is used as the admin password, please change the password before upgrading to the new firmware version. If the character "%" is used as the admin password and you've upgraded to the new firmware version without changing the password, please use the following CLI commands via Telnet/SSH to change the admin password.
 - enable
 - configure system
 - admin_passwd